

## USER GUIDE

### UGxxx | Using the PSpice Libraries



Ella Wu

## 1. INTRODUCTION

PSpice is a SPICE circuit simulator application for the simulation and verification of analog and mixed-signal circuits. It integrates easily with Cadence PCB schematic entry solutions like OrCAD Capture and comes with an easy-to-use graphical user interface.

For any new users of a tool, the basic functionalities must be learned before the tool can be put to use. For PSpice, knowing how to correctly install and find the models is crucial. Our PSpice models consist of a symbol file (\*.olb) and a netlist file (\*.lib). Our models are available on these platforms: Würth Elektronik homepage and GitHub repository.

Note: The following instructions are base on PSpice versions 2023.

## 2. INSTALLING THE LIBRARIES

### 2.1 Downloads from Würth Homepage

All our latest Eagle libraries can be downloaded from the Würth Elektronik homepage.

Browse [www.we-online.com](http://www.we-online.com) >> Components >> Find the product unit according to the catalog.




Figure 1: Würth Elektronik homepage

Or enter a search term such as part number or series.

# USER GUIDE

## UGxxx | Using the Pspice Model Libraries




Figure 2: Search part number or series

Enter Product series page >> expand the Downloads dropdown for the desired part number >> click Eagle file to download it.




Figure 3: Download PSpice libraries on Würth Homepage

### 2.2 Save the Libraries

Note: This step is optional but allows you to quickly find the libraries in the next step of the installation, you can skip this step to store the library files in any folder, but you need to remember the path where you stored the libraries.

If the PSpice libraries are only being used in a certain schematic, the symbol file (\*.olb) and netlist file (\*.lib) can be saved in the same local folder as the schematic file (\*.DSN) and the project file(\*.opj).

SYS (C:) > MyProject		
Name	Type	Size
MyProject-PSpiceFiles	File folder	
Disclaimer_READ_ME.txt	Text Document	1 KB
MYPROJECT.DSN	DSN File	10 KB
MYPROJECT.DSNlck	DSNLCK File	16 KB
MyProject.opj	OPJ File	1 KB
WE-TMSB.lib	LIB File	4 KB
WE-TMSB.OLB	OLB File	32 KB

Figure 4: Model files in same folder as schematic

### 2.3 Install the Local Libraries

Run OrCAD Capture, open or create a project and open schematic page.

Click the Place Part symbol from the toolbar on the left (or type 'P'). Or select Place in Toolbar on the top >> Part




Figure 5: Place Part

Add the Library to your project by clicking the Add Library symbol on Place Part window (or type 'Alt+A'), then Browse File and select the desired symbol file (\*.olb) and click open.




Figure 6: Add Library

Choose the desired part number by double-clicking and place the symbol in the schematic.




Figure 7: Place Component

### 2.4 Configure Netlist File

This step is very critical, only correctly configured netlist files, we can run the simulation properly.

Select PSpice in Toolbar >> New simulation Profile or Edit Simulation Profile If you have already created a Simulation Profile.




Figure 8: New or Edit Simulation Profile

Configuration Files >> Library >> Browse File and select the desired netlist file (\*.lib) and click open.




Figure 9: Add Netlist File

Select Add as Global or Add to Design. if the component is used in more than one project, add it as a global item. Click OK and save the simulation profile.




Figure 10: Add as Global or Design

### 3. INSTALL FROM GITHUB REPOSITORY

#### 3.1 Install GitHub Desktop

GitHub Desktop is the most user-friendly tool for working with GitHub projects, and we recommend you use it for keeping your library files up to date.

Go to <https://desktop.github.com/> to download the appropriate package for your operating system and install it on your computer.

During the Desktop installation, register or sign in with your GitHub Account and click next. On the opening GitHub Browser webpage authenticate yourself and give permission to the GitHub desktop application. Then the process jumps back to the Desktop tool/application.

#### 3.2 Clone the Library

From GitHub Desktop, click the button Clone a repository from the Internet as shown in the following screen in Figure 13.

Let's get started!

Add a repository to GitHub Desktop to start collaborating




Figure 11: Clone a repository from the Internet

Enter the URL of Würth Elektronik Eagle Library repository <https://github.com/WurthElektronik/Pspice-Library.git> and define the local directory to clone the repository.

Then click the **Clone** button, all the files from the online repository will begin to synchronize into local.




Figure 12: Clone Setup

Cloning repository will take some time.




Figure 13: Clone in progress

### 3.3 Synchronize Local Library from GitHub

If there are updates in GitHub repository, GitHub Desktop will detect it and you can “Pull” the update to your local. If there are any new commits on the online master repository, from GitHub Desktop you’ll receive the update information automatically. Click **Pull origin** button to fetch the updates to local folder immediately.




Figure 14: Local repository update option

Click **View on GitHub** to explore more details of the latest updates.







 hywu-eisos Upload User Manual	6c9b5d9 · 2 minutes ago	 4 Commits
 library	create folder	14 minutes ago
 symbol	create folder	14 minutes ago
 README.md	Create README.md	2 days ago
 User Manual - WE Pspice Library.pdf	Upload User Manual	2 minutes ago

Figure 15: View the updates on GitHub

### IMPORTANT NOTICE

The Application Note is based on our knowledge and experience of typical requirements concerning these areas. It serves as general guidance and should not be construed as a commitment for the suitability for customer applications by Würth Elektronik eiSos GmbH & Co. KG. The information in the Application Note is subject to change without notice. This document and parts thereof must not be reproduced or copied without written permission, and contents thereof must not be imparted to a third party nor be used for any unauthorized purpose.

Würth Elektronik eiSos GmbH & Co. KG and its subsidiaries and affiliates (WE) are not liable for application assistance of any kind. Customers may use WE's assistance and product recommendations for their applications and design. The responsibility for the applicability and use of WE Products in a particular customer design is always solely within the authority of the customer. Due to this fact it is up to the customer to evaluate and investigate, where appropriate, and decide whether the device with the specific product characteristics described in the product specification is valid and suitable for the respective customer application or not.

The technical specifications are stated in the current data sheet of the products. Therefore the customers shall use the data sheets and are cautioned to verify that data sheets are current. The current data sheets can be downloaded at [www.we-online.com](http://www.we-online.com). Customers shall strictly observe any product-specific notes, cautions and warnings. WE reserves the right to make corrections, modifications, enhancements, improvements, and other changes to its products and services.

WE DOES NOT WARRANT OR REPRESENT THAT ANY LICENSE, EITHER EXPRESS OR IMPLIED, IS GRANTED UNDER ANY PATENT

RIGHT, COPYRIGHT, MASK WORK RIGHT, OR OTHER INTELLECTUAL PROPERTY RIGHT RELATING TO ANY COMBINATION, MACHINE, OR PROCESS IN WHICH WE PRODUCTS OR SERVICES ARE USED. INFORMATION PUBLISHED BY WE REGARDING THIRD-PARTY PRODUCTS OR SERVICES DOES NOT CONSTITUTE A LICENSE FROM WE TO USE SUCH PRODUCTS OR SERVICES OR A WARRANTY OR ENDORSEMENT THEREOF.

WE products are not authorized for use in safety-critical applications, or where a failure of the product is reasonably expected to cause severe personal injury or death. Moreover, WE products are neither designed nor intended for use in areas such as military, aerospace, aviation, nuclear control, submarine, transportation (automotive control, train control, ship control), transportation signal, disaster prevention, medical, public information network etc. Customers shall inform WE about the intent of such usage before design-in stage. In certain customer applications requiring a very high level of safety and in which the malfunction or failure of an electronic component could endanger human life or health, customers must ensure that they have all necessary expertise in the safety and regulatory ramifications of their applications. Customers acknowledge and agree that they are solely responsible for all legal, regulatory and safety-related requirements concerning their products and any use of WE products in such safety-critical applications, notwithstanding any applications-related information or support that may be provided by WE.

CUSTOMERS SHALL INDEMNIFY WE AGAINST ANY DAMAGES ARISING OUT OF THE USE OF WE PRODUCTS IN SUCH SAFETY-CRITICAL APPLICATIONS

### USEFUL LINKS



Application Notes

[www.we-online.com/appnotes](http://www.we-online.com/appnotes)



**REDEXPERT** Design Platform

[www.we-online.com/redexpert](http://www.we-online.com/redexpert)



Toolbox

[www.we-online.com/toolbox](http://www.we-online.com/toolbox)



Product Catalog

[www.we-online.com/products](http://www.we-online.com/products)

### CONTACT INFORMATION

[appnotes@we-online.com](mailto:appnotes@we-online.com)

Tel. +49 7942 945 - 0



Würth Elektronik eiSos GmbH & Co. KG  
Max-Eyth-Str. 1 · 74638 Waldenburg  
Germany



[www.we-online.com](http://www.we-online.com)